License activation

Prerequisites

The free evaluation can be used once per computer, and requires network access to www.license.tomkod.com The license activation requires network access to www.tomkod.com Please check your firewall in case of failure.

Activation form

The activation window automatically shows up when the plugin is loading and a valid license or trial is not registered. If you want to see, change or remove your license while the plugin is already loaded, you can use the Rhino commands **PluginName_License**.

Table - User Manual


Introduction

Table is a plugin for Rhino 3D, designed to add the possibility to create, import or edit spreadsheets in your Rhino document.

Plugin installation

The plugin installer can be downloaded at: https://www.tomkod.com/product/tables/ A free trial is included, and yearly licenses can be purchased on the aforementioned page. *Table* works for both Rhino 5¹⁾ and Rhino 6²⁾, but some features only exist in the Rhino 6 version.

Our *Table* plugin is also compatible with <u>Yak</u>, Rhino's new package manager. You can install it from the repository with the following command line:



Last update: 2020/09/11 start:plugins:table:table-usermanual https://wiki.tomkod.com/doku.php?id=start:plugins:table:table-usermanual&rev=1599812492 10:21

Activation status is always visible on the upper right corner of the form, if the icon is green your plugin will be enabled:



Trial Tab

This first tab is dedicated to the trial requests. Your trial status is displayed, and the button is disabled if a trial is not available for your computer (Your trial has already been activated, or the server is unreachable)

TomKod license activation - 1	fable 3.x ?	×
FomKod >	Plugin Status	
oftwares for users, by users	Enabled - license is valid	2
Free Trial License Commercial Lic	cense Details	
Computer ID:	a ward	
		e1.7
Reg	uest Free evaluation (*)	
1.000	Construction and a second s	
Datas Association		
Status: Accepted (End d	ate: 21/12/2020)	
Status: Accepted (End d	ate: 21/12/2020)	
(*) This button will be - An evaluation i	e greyed out in the following cases:	
(*) This button will be - An evaluation - Our server is u	e greyed out in the following cases:	

Commercial Tab

This tab's two main buttons let you Check-out (Activate) or Check-in (Desactivate) your license from our license server.

TomKod Softwares for user		Plugin Status Enabled - <mark>lic</mark> ense is valid	0
Free Trial License	Commercial License	Details	
Email		.com	
Product key			
	ate (Check-Out) abled	Desactivate (Ch	
Enable floa	ting licenses (Affect	s every TomKod plugins)	
Use a license ce	rtficate		
	sative method for offi	ine activation, using a certificat	
		on issues, but the license won't	be soasng.

When the checkbox "*Enable floating licenses*" is checked, every TomKod's plugin will try to deactivate the license automatically when closing (Making it available for another of your computers)

Finally, a license certificate (*.TkLic) can be selected at the bottom of this tab. It allows to activate a license offline, but the license won't be floating anymore. If you need one, contact us at https://www.tomkod.com/contact/

Toolbar

The toolbars for Rhino are always included in your plugins installation directory, or can be downloaded here.

You just have to drag/drop the file "Tomkod.rui" to a rhino window to install them.

Features and commands

Table_About

This command can be used only from the command line prompt. It displays the plugin's current revision and license status.

Last update: 2020/09/11 start:plugins:table:table-usermanual https://wiki.tomkod.com/doku.php?id=start:plugins:table:table-usermanual&rev=1599812492 10:21

Commercial Name: Table 3.x			
Update Status: Table 3.x: Your current version (3.1.2.0) is an early rele	ease candidate.	Latest stable ven	sion: 3.1.1
Editor: TomKod			
Copyright: Copyright @Ship-ST 2020			
License status:			
Commercial license: Disabled			
Trial status: Accepted			
Computer ID: TomKodDevComputerUniqueID			
CHANGELOG:			
>			
v3.1.2 (21 dec. 2020)			
Added: Keywords for yak package			
6 available commands			
Table_License			
Table_About			
TableCreate			
TableEdit			
Table:Reload			

TableCreate

Walkthrough

The command **TableCreate** allows to create a new table directly from Rhino. At first it will show a basic spreadsheet editor:

This					
	is				
		A			
			Test		
1	2	3	4	5	


Afterward, the user will be able to pick the Table's insertion point, with a realtime preview.³⁾

This i	sa	title		_
This				-
i i	is	1	ť.	
1		A	1	
			Test	
1	2	3	4	5

Options

TableLocation (EontHeights 10 Corners Upper(eff] Bellows/Nore Fgnt)

- FontHeight: Takes a number for the text height.
- Font: Pops up a dialog to let the user select the required font family.



TableEdit

The command **TableEdit**⁴⁾ allows to edit a table created or imported with our plugin. It works exactly the same as the command TableCreate, except that the user will be asked to select an existing table to edit.

The same spreadsheet editor and options are available.

TableImport

Walkthrough

The command TableImport allows to import a spreadsheet from an Excel file (.xls, .xlsx) or from a csv file (.csv). After launching the command, a dialog offer to select a compatible file:

< ↑ 📕 = Te	able > TestsFiles		~ U	Rechercher dans : T	estsFi	les .	P
Organiser • Nouveau	i dossier			10			0
·	Nom	Modifié le	Type		Taitle		
* Accès rapide	📓 test.xisx	2020-06-29 09:56	Feuill	e de calcul Micr		9 Ko	
Documents # Téléchargem #							

If the excel file has several worksheets, the user will be asked to pick one among the list:

Sheet1		
Sheet2		1
	OK	Cancel

Scripted mode

This command can be scripted using RhinoScript or your own macros:

Command: -TableImport Information: In scripted mode, your csv file must use ";" as separator. Enter a file path to import (*.csv, *.xls, *.xlsx):

Options

TableLocation (EontHeight= 10 Corners Lipper(eff [BieRows-Nore Fgnt) |

- FontHeight: Takes a number for the text height.
- Font: Pops up a dialog to let the user select the required font family.

Please select a for	t.	
AcadEref		0
AIGDT		
AmdtSymbols		
AMGDT		
Amienne		
Arial		
Arial Black		
Amprior		
Bahnschrift		
Bahnschrift Cond	lensed	
	OK	Cancel

TablesReload

This command will reload every tables in the document from their original document (.xls, .xlsx, .csv). The tables whose original file has been deleted or moved will be ignored, as well as tables created inside Rhino.

```
1)
Rhino5.12 or later
2)
Rhino6.15 or later
3)
```

In rhino5, the preview might not display the texts with the selected font

Only available with Rhino 6

From:

4)

https://wiki.tomkod.com/ - TomKod knowledge base

Permanent link:

https://wiki.tomkod.com/doku.php?id=start:plugins:table:table-usermanual&rev=1599812492

Last update: 2020/09/11 10:21

